# Arduino Weather Sensor Driver

Generated by Doxygen 1.8.9.1

Wed Aug 19 2015 01:07:08

## Contents

1	Hier	Hierarchical Index 1						
	1.1	Class Hierarchy	1					
2	Clas	lass Index 2						
	2.1 Class List							
3	File	Index	2					
3.1 File List								
4	Clas	es Documentation	2					
	4.1	WeatherSensor Class Reference	2					
		4.1.1 Detailed Description	3					
		4.1.2 Member Function Documentation	3					
	4.2	WeatherSensorDHT11 Class Reference	3					
		4.2.1 Detailed Description	4					
		4.2.2 Member Enumeration Documentation	5					
		4.2.3 Constructor & Destructor Documentation	5					
		4.2.4 Member Function Documentation	5					
		4.2.5 Member Data Documentation	6					
5 File Documentation								
	5.1 WeatherSensor.cpp File Reference							
		5.1.1 Macro Definition Documentation	7					
	5.2 WeatherSensor.cpp							
		5.5.1 Macro Definition Documentation	9					
	5.6 WeatherSensorDHT11.cpp		9					
			11					
		5.7.1 Macro Definition Documentation	12					
	5.8	WeatherSensorDHT11.h	12					
Index								
1	1 Hierarchical Index							
1.1	Cla	ass Hierarchy						
Thi	s inhe	eritance list is sorted roughly, but not completely, alphabetically:						
WeatherSensor 2								

WeatherSensorDHT11 3

### 2 Class Index

### 2.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

#### WeatherSensor

Arduino - Weather sensor

WeatherSensorDHT11

### 3 File Index

### 3.1 File List

Here is a list of all files with brief descriptions:


WeatherSensor.cpp 7
WeatherSensor.h 8
WeatherSensorDHT11.cpp 9
WeatherSensorDHT11.h 11

### 4 Class Documentation

### 4.1 WeatherSensor Class Reference

#include <WeatherSensor.h>

Inheritance diagram for WeatherSensor:



**Public Member Functions** 

- virtual float getHumidity ()=0
- virtual float getTemperature ()=0

### 4.1.1 Detailed Description

Arduino - Weather sensor.

WeatherSensor.h

The abstract class for the weather sensors.

Author

Dalmir da Silva dalmirdasilva@gmail.com

Definition at line 14 of file WeatherSensor.h.

### 4.1.2 Member Function Documentation

4.1.2.1 virtual float WeatherSensor::getHumidity() [pure virtual]

Returns the air humidity.

The air humidity.

Implemented in WeatherSensorDHT11.

**4.1.2.2** virtual float WeatherSensor::getTemperature() [pure virtual]

Returns the temperature.

The temperature.

Implemented in WeatherSensorDHT11.


The documentation for this class was generated from the following file:

· WeatherSensor.h


### 4.2 WeatherSensorDHT11 Class Reference

#include <WeatherSensorDHT11.h>

Inheritance diagram for WeatherSensorDHT11:



### Collaboration diagram for WeatherSensorDHT11:



### **Public Types**

enum Code {
 SUCCESS = 0x00, ERROR\_CHECKSUM = 0x01, ERROR\_CONDITION1\_NOT\_MET = 0x02, ERROR\_C
 ONDITION2\_NOT\_MET = 0x04,
 ERROR\_CONDITION3\_NOT\_MET = 0x08 }

### **Public Member Functions**

- WeatherSensorDHT11 (unsigned char dataPin)
- float getHumidity ()
- float getTemperature ()
- Code getLastCode ()

#### **Private Member Functions**

- · Code readPackage (unsigned char \*buf)
- float makeFloat (unsigned char \*buf)
- bool isAvailable ()
- unsigned char read ()
- · unsigned long waitFor (unsigned char pin, unsigned char state, unsigned long timeout)

### **Private Attributes**

- unsigned char buf [5]
- unsigned char dataPin
- unsigned long lastReadTime
- · float lastHumity
- float lastTemperature
- Code lastCode

### 4.2.1 Detailed Description

Definition at line 37 of file WeatherSensorDHT11.h.

```
4.2.2 Member Enumeration Documentation
```

4.2.2.1 enum WeatherSensorDHT11::Code

Enumerator

**SUCCESS** 

ERROR\_CHECKSUM

ERROR CONDITION1\_NOT\_MET

ERROR\_CONDITION2\_NOT\_MET

ERROR\_CONDITION3\_NOT\_MET

Definition at line 66 of file WeatherSensorDHT11.h.

4.2.3 Constructor & Destructor Documentation

4.2.3.1 WeatherSensorDHT11::WeatherSensorDHT11 (unsigned char dataPin)

Public constructor.

**Parameters** 

dataPin The data pin.

Definition at line 16 of file WeatherSensorDHT11.cpp.

4.2.4 Member Function Documentation

**4.2.4.1** float WeatherSensorDHT11::getHumidity() [virtual]

Returns the air humidity.

The air humidity.

Implements WeatherSensor.

Definition at line 26 of file WeatherSensorDHT11.cpp.

**4.2.4.2 Code WeatherSensorDHT11::getLastCode( )** [inline]

Gets the last read code.

Returns

Definition at line 100 of file WeatherSensorDHT11.h.

**4.2.4.3** float WeatherSensorDHT11::getTemperature() [virtual]

Returns the temperature.

The temperature.

Implements WeatherSensor.

Definition at line 33 of file WeatherSensorDHT11.cpp.

**4.2.4.4 bool WeatherSensorDHT11::isAvailable( )** [private]

Return true if the device is available for a read operation.

Returns

Definition at line 40 of file WeatherSensorDHT11.cpp.

**4.2.4.5** float WeatherSensorDHT11::makeFloat ( unsigned char \* buf ) [private]

Makes a float number from a read data.

**Parameters** 

```
buf | The read data.
```

Returns

The float conversion.

Definition at line 113 of file WeatherSensorDHT11.cpp.

**4.2.4.6 unsigned char WeatherSensorDHT11::read()** [private]

Reads a byte from the device.

Returns

Definition at line 81 of file WeatherSensorDHT11.cpp.

4.2.4.7 WeatherSensorDHT11::Code WeatherSensorDHT11::readPackage (unsigned char \* buf ) [private]

Reads 5 bytes from the device.

1st byte: Integer part of the humidity. 2nd byte: Fractional part of the humidity. 3th byte: Integer part of the temperature. 4th byte: Fractional part of the temperature. 5th byte: Checksum.

Returns

The error code.

Definition at line 44 of file WeatherSensorDHT11.cpp.

**4.2.4.8** unsigned long WeatherSensorDHT11::waitFor ( unsigned char *pin*, unsigned char *state*, unsigned long *timeout* ) [private]

Waits for a given state on a input pin.

Definition at line 96 of file WeatherSensorDHT11.cpp.

4.2.5 Member Data Documentation

**4.2.5.1 unsigned char WeatherSensorDHT11::buf[5]** [private]

A internal buffer.

Definition at line 42 of file WeatherSensorDHT11.h.

**4.2.5.2** unsigned char WeatherSensorDHT11::dataPin [private]

The data pin.

Definition at line 47 of file WeatherSensorDHT11.h.

5 File Documentation 7

**4.2.5.3 Code WeatherSensorDHT11::lastCode** [private]

Definition at line 106 of file WeatherSensorDHT11.h.

**4.2.5.4 float WeatherSensorDHT11::lastHumity** [private]

The last humity.

Definition at line 57 of file WeatherSensorDHT11.h.

**4.2.5.5** unsigned long WeatherSensorDHT11::lastReadTime [private]

The last read time.

Definition at line 52 of file WeatherSensorDHT11.h.

**4.2.5.6** float WeatherSensorDHT11::lastTemperature [private]

The last temperature.

Definition at line 62 of file WeatherSensorDHT11.h.


The documentation for this class was generated from the following files:

- WeatherSensorDHT11.h
- WeatherSensorDHT11.cpp

### 5 File Documentation

### 5.1 WeatherSensor.cpp File Reference

#include "WeatherSensor.h"
Include dependency graph for WeatherSensor.cpp:



#### **Macros**

- #define \_\_ARDUINO\_DRIVER\_WEATHER\_SENSOR\_CPP\_\_ 1
- 5.1.1 Macro Definition Documentation
- 5.1.1.1 #define \_\_ARDUINO\_DRIVER\_WEATHER\_SENSOR\_CPP\_\_1

Arduino - Weather sensor.

### WeatherSensor.h

The abstract class for the color sensors.

**Author** 

Dalmir da Silva dalmirdasilva@gmail.com


Definition at line 12 of file WeatherSensor.cpp.

### 5.2 WeatherSensor.cpp

```
00001
00011 #ifndef __ARDUINO_DRIVER_WEATHER_SENSOR_CPP_
00012 #define __ARDUINO_DRIVER_WEATHER_SENSOR_CPP_ 1
00013
00014 #include "WeatherSensor.h"
00015
00016 #endif /* __ARDUINO_DRIVER_WEATHER_SENSOR_CPP__ */
```

### 5.3 WeatherSensor.h File Reference

This graph shows which files directly or indirectly include this file:



### Classes


· class WeatherSensor

### 5.4 WeatherSensor.h

```
00001
00011 #ifndef __ARDUINO_DRIVER_WEATHER_SENSOR_H_
00012 #define __ARDUINO_DRIVER_WEATHER_SENSOR_H_ 1
00013
00014 class WeatherSensor {
00015 public:
00016
00022     virtual float getHumidity() = 0;
00023
00029     virtual float getTemperature() = 0;
00030 };
00030 };
00031
00032 #endif /* __ARDUINO_DRIVER_WEATHER_SENSOR_H__ */
```

### 5.5 WeatherSensorDHT11.cpp File Reference

#include "WeatherSensorDHT11.h"
Include dependency graph for WeatherSensorDHT11.cpp:



#### Macros

• #define \_\_ARDUINO\_DRIVER\_WEATHER\_SENSOR\_DHT11\_CPP\_\_1

#### 5.5.1 Macro Definition Documentation

#### 5.5.1.1 #define \_\_ARDUINO\_DRIVER\_WEATHER\_SENSOR\_DHT11\_CPP\_\_ 1

Arduino - Weather sensor.

#### WeatherSensorDHT11.h

The class for the DHT11 weather sensor.

Author

Dalmir da Silva dalmirdasilva@gmail.com

Definition at line 12 of file WeatherSensorDHT11.cpp.

### 5.6 WeatherSensorDHT11.cpp

```
00001
00011 #ifndef __ARDUINO_DRIVER_WEATHER_SENSOR_DHT11_CPP_
00012 #define __ARDUINO_DRIVER_WEATHER_SENSOR_DHT11_CPP__ 1
00013
00014 #include "WeatherSensorDHT11.h"
00015
00016 WeatherSensorDHT11::WeatherSensorDHT11(unsigned char dataPin) :
00017
             dataPin(dataPin) {
00018
          lastReadTime = millis() - WEATHER_MILLIS_BETWEEN_READS;
00019
          lastHumity = 0.0;
00020
          lastTemperature = 0.0;
00021
          lastCode = SUCCESS:
00022
          pinMode(dataPin, OUTPUT);
00023
          digitalWrite(dataPin, HIGH);
00024 }
00025
00026 float WeatherSensorDHT11::getHumidity() {
00027
        if (isAvailable()) {
00028
              lastCode = readPackage(this->buf);
00029
00030
          return lastHumity;
00031 }
```


```
00032
00033 float WeatherSensorDHT11::getTemperature() {
00034
          if (isAvailable()) {
00035
              lastCode = readPackage(this->buf);
00036
00037
          return lastTemperature:
00039
00040 bool WeatherSensorDHT11::isAvailable() {
00041
          return (lastReadTime + WEATHER_MILLIS_BETWEEN_READS) <= millis(</pre>
00042 }
00043
00044 WeatherSensorDHT11::Code WeatherSensorDHT11::readPackage
      (unsigned char *buf) {
          unsigned char in, checkSum;
unsigned long m = 0;
00045
00046
00047
          while (!isAvailable())
00049
           lastReadTime = millis();
00050
          pinMode(dataPin, OUTPUT);
00051
           digitalWrite(dataPin, LOW);
          delay(WEATHER_REQUEST_LOW_LENGTH);
00052
00053
          digitalWrite(dataPin, HIGH);
00054
          pinMode(dataPin, INPUT);
00055
          m = waitFor(dataPin, LOW, WEATHER_REQUEST_HIGH_LENGTH);
00056
          if (m == 0) {
00057
              return ERROR_CONDITION1_NOT_MET;
00058
          m = waitFor(dataPin, HIGH, WEATHER_RESPONSE_LOW_LENGTH);
00059
00060
          if (m == 0) {
00061
              return ERROR_CONDITION2_NOT_MET;
00062
00063
          m = waitFor(dataPin, LOW, WEATHER_RESPONSE_HIGH_LENGTH);
          if (m == 0) {
    return ERROR_CONDITION3_NOT_MET;
00064
00065
00066
00067
          for (unsigned char i = 0; i < 5; i++) {
00068
              buf[i] = read();
00069
00070
          pinMode(dataPin, OUTPUT);
00071
          digitalWrite(dataPin, HIGH);
          checkSum = buf[0] + buf[1] + buf[2] + buf[3];
if (buf[4] != checkSum) {
00072
00073
00074
              return ERROR_CHECKSUM;
00075
00076
          lastHumity = makeFloat(this->buf);
00077
          lastTemperature = makeFloat(&(this->buf[2]));
00078
          return SUCCESS;
00079 }
00080
00081 unsigned char WeatherSensorDHT11::read() {
          unsigned char d = 0;
unsigned long m = 0;
00082
00083
          for (unsigned char i = 0; i < 8; i++) {</pre>
00084
              m = waitFor(dataPin, HIGH, WEATHER_START_TRANSMIT_LENGTH
00085
      );
00086
               if (m > 0) {
                  m = waitFor(dataPin, LOW, WEATHER_ONE_LENGTH);
if (m > WEATHER_ZERO_LENGTH) {
00087
00088
                       d \mid = (1 << (7 - i));
00089
00090
00091
               }
00092
           return d;
00093
00094 }
00095
00096 unsigned long WeatherSensorDHT11::waitFor(unsigned char pin,
00097
              unsigned char state, unsigned long timeout) {
          unsigned char bit = digitalPinToBitMask(pin);
00098
00099
          unsigned char port = digitalPinToPort(pin);
00100
          unsigned char stateMask = (state ? bit : 0);
00101
          unsigned long width = 0;
          unsigned long numloops = 0;
00102
          unsigned long maxloops = microsecondsToClockCycles(timeout) / 16;
00103
          while ((*portInputRegister(port) & bit) != stateMask) {
00104
00105
              if (numloops++ == maxloops) {
00106
                   return 0;
00107
               width++:
00108
00109
00110
          return clockCyclesToMicroseconds(width * 21 + 8);
00111 }
00112
00113 float WeatherSensorDHT11::makeFloat(unsigned char *buf) {
          float f = 0.0;
f += *buf;
00114
00115
```

```
00116     f += *(buf + 1) / 256.0;
00117     return f;
00118 }
00119
00120 #endif /* __ARDUINO_DRIVER_WEATHER_SENSOR_DHT11_CPP__ */
```


### 5.7 WeatherSensorDHT11.h File Reference

```
#include <WeatherSensor.h>
#include <Arduino.h>
#include <wiring_private.h>
#include <pins_arduino.h>
```

Include dependency graph for WeatherSensorDHT11.h:



This graph shows which files directly or indirectly include this file:



#### Classes

• class WeatherSensorDHT11

### Macros

- #define WEATHER\_MILLIS\_BETWEEN\_READS 800
- #define WEATHER\_REQUEST\_LOW\_LENGTH 20
- #define WEATHER\_REQUEST\_HIGH\_LENGTH 40
- #define WEATHER RESPONSE LOW LENGTH 80
- #define WEATHER\_RESPONSE\_HIGH\_LENGTH 80
- #define WEATHER\_START\_TRANSMIT\_LENGTH 50
- #define WEATHER\_ZERO\_LENGTH 40
- #define WEATHER\_ONE\_LENGTH 70

#### 5.7.1 Macro Definition Documentation

### 5.7.1.1 #define WEATHER\_MILLIS\_BETWEEN\_READS 800

Arduino - Weather sensor.

#### WeatherSensorDHT11.h

The class for the DHT11 weather sensor.

**Author** 

Dalmir da Silva dalmirdasilva@gmail.com The time between consecutive reads.

#### **Parameters**

```
dataPin
```

Definition at line 24 of file WeatherSensorDHT11.h.

5.7.1.2 #define WEATHER\_ONE\_LENGTH 70

Definition at line 35 of file WeatherSensorDHT11.h.

5.7.1.3 #define WEATHER REQUEST HIGH LENGTH 40

Definition at line 27 of file WeatherSensorDHT11.h.

5.7.1.4 #define WEATHER\_REQUEST\_LOW\_LENGTH 20

Definition at line 26 of file WeatherSensorDHT11.h.

5.7.1.5 #define WEATHER\_RESPONSE\_HIGH\_LENGTH 80

Definition at line 30 of file WeatherSensorDHT11.h.

5.7.1.6 #define WEATHER\_RESPONSE\_LOW\_LENGTH 80

Definition at line 29 of file WeatherSensorDHT11.h.

5.7.1.7 #define WEATHER\_START\_TRANSMIT\_LENGTH 50

Definition at line 32 of file WeatherSensorDHT11.h.

5.7.1.8 #define WEATHER\_ZERO\_LENGTH 40

Definition at line 34 of file WeatherSensorDHT11.h.

### 5.8 WeatherSensorDHT11.h

```
00001
00011 #ifndef __ARDUINO_DRIVER_WEATHER_SENSOR_DHT11_H_
00012 #define __ARDUINO_DRIVER_WEATHER_SENSOR_DHT11_H_ 1
00013
00014 #include <WeatherSensor.h>
00015 #include <Arduino.h>
00016 #include <wiring_private.h>
00017 #include <pins_arduino.h>
00018
                                                      800
00024 #define WEATHER MILLIS BETWEEN READS
00025
00026 #define WEATHER_REQUEST_LOW_LENGTH
00027 #define WEATHER_REQUEST_HIGH_LENGTH
                                                       40
00028
00029 #define WEATHER RESPONSE LOW LENGTH
                                                      80
00030 #define WEATHER_RESPONSE_HIGH_LENGTH
00031
00032 #define WEATHER_START_TRANSMIT_LENGTH
```

```
00033
00034 #define WEATHER_ZERO_LENGTH
00035 #define WEATHER_ONE_LENGTH
00036
00037 class WeatherSensorDHT11 : public WeatherSensor {
00038
          unsigned char buf[5];
00043
00047
          unsigned char dataPin;
00048
00052
          unsigned long lastReadTime;
00053
00057
          float lastHumity;
00058
00062
          float lastTemperature;
00063
00064 public:
00065
00066
          enum Code {
00067
              SUCCESS = 0x00,
00068
              ERROR_CHECKSUM = 0 \times 01,
              ERROR_CONDITION1_NOT_MET = 0x02,
ERROR_CONDITION2_NOT_MET = 0x04,
00069
00070
              ERROR_CONDITION3_NOT_MET = 0x08
00071
00072
          };
00073
00079
          WeatherSensorDHT11(unsigned char dataPin);
08000
          float getHumidity();
00086
00087
00093
          float getTemperature();
00094
00100
          Code getLastCode() {
00101
              return lastCode;
00102
00103
00104 private:
00105
00106
          Code lastCode;
00107
00119
          Code readPackage(unsigned char *buf);
00120
00127
          float makeFloat (unsigned char *buf);
00128
00134
          bool isAvailable();
00135
00141
          unsigned char read();
00142
00146
          unsigned long waitFor (unsigned char pin, unsigned char state, unsigned long timeout);
00147 };
00148
00149 #endif /* __ARDUINO_DRIVER_WEATHER_SENSOR_DHT11_H__ */
```

## Index

$\_{ARDUINO\_DRIVER\_WEATHER\_SENSOR\_CPP\_} \leftarrow$	WeatherSensorDHT11.h, 12		
_	WEATHER_ONE_LENGTH		
WeatherSensor.cpp, 7	WeatherSensorDHT11.h, 12		
ARDUINO_DRIVER_WEATHER_SENSOR_DH	WEATHER_REQUEST_HIGH_LENGTH		
T11 CPP	WeatherSensorDHT11.h, 12		
WeatherSensorDHT11.cpp, 9	WEATHER_REQUEST_LOW_LENGTH		
117	WeatherSensorDHT11.h, 12		
buf	WEATHER_RESPONSE_HIGH_LENGTH		
WeatherSensorDHT11, 6	WeatherSensorDHT11.h, 12		
	WEATHER RESPONSE LOW LENGTH		
Code			
WeatherSensorDHT11, 5	WeatherSensorDHT11.h, 12		
	WEATHER_START_TRANSMIT_LENGTH		
dataPin	WeatherSensorDHT11.h, 12		
WeatherSensorDHT11, 6	WEATHER_ZERO_LENGTH		
	WeatherSensorDHT11.h, 12		
ERROR_CHECKSUM	waitFor		
WeatherSensorDHT11, 5	WeatherSensorDHT11, 6		
ERROR_CONDITION1_NOT_MET	WeatherSensor, 2		
WeatherSensorDHT11, 5	getHumidity, 3		
ERROR_CONDITION2_NOT_MET	getTemperature, 3		
WeatherSensorDHT11, 5	WeatherSensor.cpp, 7, 8		
ERROR_CONDITION3_NOT_MET	ARDUINO_DRIVER_WEATHER_SENSOR_		
WeatherSensorDHT11, 5	CPP , 7		
	WeatherSensor.h, 8		
getHumidity	WeatherSensorDHT11, 3		
WeatherSensor, 3	buf, 6		
WeatherSensorDHT11, 5	Code, 5		
getLastCode			
WeatherSensorDHT11, 5	dataPin, 6		
getTemperature	ERROR_CHECKSUM, 5		
WeatherSensor, 3	ERROR_CONDITION1_NOT_MET, 5		
WeatherSensorDHT11, 5	ERROR_CONDITION2_NOT_MET, 5		
Trouble Control Bill 11, 0	ERROR_CONDITION3_NOT_MET, 5		
isAvailable	getHumidity, 5		
WeatherSensorDHT11, 5	getLastCode, 5		
,,,	getTemperature, 5		
lastCode	isAvailable, 5		
WeatherSensorDHT11, 6	lastCode, 6		
lastHumity	lastHumity, 7		
WeatherSensorDHT11, 7	lastReadTime, 7		
lastReadTime	lastTemperature, 7		
WeatherSensorDHT11, 7	makeFloat, 6		
lastTemperature	read, 6		
WeatherSensorDHT11, 7	readPackage, 6		
Trouble Control Bill 11, 7	SUCCESS, 5		
makeFloat	waitFor, 6		
WeatherSensorDHT11, 6	WeatherSensorDHT11, 5		
,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,	•		
read	WeatherSensorDHT11.cpp, 9		
WeatherSensorDHT11, 6	ARDUINO_DRIVER_WEATHER_SENSOR_		
readPackage	DHT11_CPP, 9		
WeatherSensorDHT11, 6	WeatherSensorDHT11.h, 11, 12		
	WEATHER_MILLIS_BETWEEN_READS, 12		
SUCCESS	WEATHER_ONE_LENGTH, 12		
WeatherSensorDHT11, 5	WEATHER_REQUEST_HIGH_LENGTH, 12		
•	WEATHER_REQUEST_LOW_LENGTH, 12		
WEATHER_MILLIS_BETWEEN_READS	WEATHER_RESPONSE_HIGH_LENGTH, 12		

16 INDEX

WEATHER\_RESPONSE\_LOW\_LENGTH, 12 WEATHER\_START\_TRANSMIT\_LENGTH, 12 WEATHER\_ZERO\_LENGTH, 12